

Gold Farmer Official User Guide



Gold Farmer

- Gold is in your future -

Gold Farmer

Full Automated EA for Stable Passive Income

Join our Telegram for the latest info, update & discount!

<https://t.me/GoldFarmerOfficial>

<https://t.me/GoldFarmerOfficialSupport>

Disclaimer:

Trading "Gold Farmer" EA involves substantial risk. It is not suitable for all investors, and potential losses may exceed your initial investment. Use it at your own risk. The developers and distributors are not liable for any financial losses incurred. Please assess your risk tolerance and financial situation before using the EA.



Installation Guide

System Requirements


1. **MetaTrader 4 from your broker installed on your PC or VPS.**
2. **Download Gold Farmer EA from your subscription email.**
3. **Inform <https://t.me/GoldFarmerOfficialSupport> your License ID and MT4 account number.**

Installation steps:


1. **Extract the downloaded EA and copy Gold Farmer Premium.ex4 to the MT4 Terminal Expert folder by opening the MT4 Terminal, under File -> Open Data Folder -> MQL4 -> Expert**



2. **Copy files inside Copy_Only_Files_Inside_To_Broker_Folder to the root of the MT4 installation folder. It is usually under C: \ Program Files (x86) \ ****Broker EA Folder**** **



3. Relaunch the MT4 Terminal
4. Attach Gold Farmer EA to the chart.
5. Allow DLL imports for the EA.



Debug:

1. If you observe unhandled exception 0xe0434352 error on your MT4, download <https://dotnet.microsoft.com/en-us/download/dotnet-framework/net48>
Or
<https://go.microsoft.com/fwlink/?linkid=2088631> to download Windows Server 2012 and install.
2. Relaunch your MT4 Platform once installation is done.

User Guide

Broker	Any low spread broker
Leverage	1:300 and above
Instrument	XAUUSD/Gold only
Time Frame	M1/M5/M15/M30
Customer ID	Your Email thru Order (Besides this, inform Gold Farmer admin your MT4 number)
Magic Number	Unique EA ID. Set different number if you use Gold Farmer more than 1 chart
Martingale Type	Multplier, apply next lot by multiplier x1, x2, x3..... Additioner, apply next lot by adding lot size
Mode	M1 Scalping, Capital <\$1500, 20%~50%/month profit M5 Scalping, Capital <\$1000, 10%~20%/month profit M15 Swing, Capital <\$800, 10~15%/month profit M30 Swing, Capital <\$500, 5~15%/month profit
Aggressive Index	Adjust EA aggressiveness High – more aggressive trades, Medium – normal trades, default Low – less and more accurate trades
Martingale multiplier	If set to multiplier to 2, LotSize = 0.01 1st Lot = 0.01, 2nd Lot = 0.02, 3rd Lot = 0.04 and ... (Only apply to Martingale Type - Multiplier)
Martingale Additioner	If set additioner 0.02, LotSize = 0.01 1st Lot = 0.01, 2nd Lot = 0.03, 3rd Lot = 0.05 and ... (Only apply to Martingale Type - Additioner)
LotSize	Starting lot size
MaxLot	Maximum allowed lot size
Distance between Trades	Minimum distance in pips before you open a new trade. Do not use any number below 30
Maximum Trades	Maximum no of trade allowed to open. If you set to 3, then it will only open 3 trades, 0.01, 0.02, 0.04.
Follow Trend	Set to True if you wish to trade following the trend

Profit Target	Take profit in pips
Trailing Start	Start profit trailing after <setting> pips. If you want to disable Trailing, set this higher than Profit Target
Trailing Step	Distance of next trailing step, do not set this lower than 5 pips
Pause Interval Option	Option to avoid over trade after profit taking
Pause Interval	Pause interval duration in minutes
Equity Protection Option	Equity Protection either with Dollar in amount OR Percentage to capital. Default is no protection.
Equity Protection % or \$	Dollar - If you set 300, EA will close all the open trades when the floating loss hit \$300 Percentage - If you set 5 (=5%), EA will close all the open trades when the floating loss hit \$300 with \$6000 capital
Resume Trade Option after Equity Protection	Either Continue Trading OR Stop Trading After Equity Protection
Allowable Holding Hours	EA will track duration from first entry trade, and will close all the trades after allowable holding hours.
RSI Filter	Enable or Disable RSI Filter for first entry lot
RSI Period	RSI duration/candle count based on current chart time frame
Upper/Lower RSI	Upper – Only allow open first Short trades if above upper RSI limit Lower – Only allow open first Lon trades if below lower RSI limit
Filter Mode	Enable news filter. Set to Disable if you wish to take more risk
News Risk Mode	Set the news filter risk level
Pause Duration Before News	Set pause duration in minutes before news
Pause Duration After News	Set pause duration in minutes after news

User guide applied to Gold Farmer Premium v8.2 and above